Pre-requisites

To get started, you need to download:


- Teradata Express 16.20 VM Image.
- VMWare Workstation 15 Player.
- Teradata tools and utilities.
- JDK 8 and other dependencies (see the download page for TD Express).
- You can download these from: Teradata Downloads page.
- An account is required, you can create one for free.

Launch your VM

- In VMWare Player's main window, right click on the VM name and select "Virtual Machine Settings".
- In the settings window, click on "Network Adapter" and among the options on the right, select "Host-only: a private network shared with the host".
- Click ok and boot your virtual machine.
- Login credentials are root/root

Connect to your DB

Open a terminal and type ifconfig. You should see an inet addr value as below.



Test connection

 On your PowerShell or UNIX console, ping the IP address of your DB with the command ping 192.168.47.129

```
Windows PowerShell
                                                                     \times
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.
PS C:\Users\HP> ping 192.168.47.129
Pinging 192.168.47.129 with 32 bytes of data:
Reply from 192.168.47.129: bytes=32 time=1ms TTL=64
Reply from 192.168.47.129: bytes=32 time<1ms TTL=64
Reply from 192.168.47.129: bytes=32 time<1ms TTL=64
Reply from 192.168.47.129: bytes=32 time<1ms TTL=64
Ping statistics for 192.168.47.129:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms
PS C:\Users\HP>
```

Connect with SQLA

- Now open SQL Assistant, and create a new connection using the IP address of your DB.
- Default credentials are dbc/dbc.
- Run a simple query.

